




Parametric Value at Risk

Parametric VaR

Value at Risk (VaR) Definition

- ◆ VaR is defined as the potential change in market value over a 1-day period at the 99% confidence level due to changes in risk factors.
- ◆ The maximum likely loss on a portfolio for a given probability



Parametric VaR

Value at Risk Pros & Cons

◆ Pros

- ◆ Regulatory measurement for market risk
- ◆ Objective assessment
- ◆ Intuition and clear interpretation
- ◆ Consistent and flexible measurement

◆ Cons

- ◆ Doesn't measure risk beyond the confidence level: tail risk
- ◆ Non sub-additive

Parametric VaR

Three Value at Risk Approaches

- ◆ Parametric Value at Risk
- ◆ Historical Value at Risk
- ◆ Monte Carlo Value at Risk

Parametric VaR

Parametric Value at Risk

◆ Assumption

Asset returns follow normal distribution

◆ Pros

Fast and simple calculation

Intuitive

◆ Cons

Poor accuracy for non-linear products

Second order approximation

Hard to incorporate stress test

Parametric VaR

Parametric Value at Risk Methodology

- ◆ Assuming an asset return/valueChange follows normal distribution, the quantile of 99% confidence level is 2.326σ where σ is standard derivation
- ◆ If absolute return $X_1 - X_0$ is normally distributed, the 99% worse change of X is $X_1 - X_0 = 2.326\sigma$
- ◆ The VaR is given by $VaR = \frac{\partial F}{\partial X} \Delta X = \frac{\partial F}{\partial X} \times 2.326 \times \sigma$ where $\frac{\partial F}{\partial X}$ is the delta
- ◆ Similarly for a relative return $\frac{X_1 - X_0}{X_0}$, the VaR can be expressed as

$$VaR = \frac{\partial F}{\partial X} \Delta X = \frac{\partial F}{\partial X} (X_1 - X_0) = \frac{\partial F}{\partial X} \times X_0 \times 2.326 \sigma$$

Parametric VaR

Parametric Value at Risk Implementation

- ◆ For each asset/instrument/riskFactor, calibrate volatility σ_i based on daily return
- ◆ For each risk factor pair, calibrate correlation ρ_{ij}
- ◆ Calculate the variance of a portfolio value change

$$V_p^2 = [\Delta(P_1)\sigma_1 \quad \dots \quad \Delta(P_n)\sigma_n] \begin{bmatrix} \rho_{11} & \dots & \rho_{1n} \\ \vdots & & \vdots \\ \rho_{n1} & \dots & \rho_{nn} \end{bmatrix} \begin{bmatrix} \Delta(P_1)\sigma_1 \\ \vdots \\ \Delta(P_n)\sigma_n \end{bmatrix}$$

- ◆ The portfolio VaR is $2.326 \sqrt{V_p^2}$

Parametric VaR

Parametric Value at Risk Implementation

- ◆ Calculate VaR values by multiplying the net PV01 values for each rating by the credit spread volatility factors for that rating. The credit spread volatility factor is the 1-day movement at the 99% confidence level based on the 2-year credit spread for a particular rating band.



Reference:

<https://finpricing.com/aboutus.html>